```
<?xml version="1.0" encoding="UTF-8"?>
<AcfSettingsDocument
  xmlns="http://www.phoenixcontact.com/schema/acfsettings"
  xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="http://www.phoenixcontact.com/schema/acfsettings.xsd"
  schemaVersion="1.0" >

  <Includes>
    <Include path="*Scm.acf.settings" />
    <Include path="$ARP_HOME_DIR$/appshome/*.acf.settings" />
  </Includes>

  <ProcessSettings singleProcess="false" />

  <LogSettings configFile="Device.log.ini" />
  <RscSettings path="/etc/plcnext/device/System/Rsc/Rsc.settings"/>
  <NmSettings path="/etc/plcnext/device/System/Nm/Nm.settings" />

  <EnvironmentSettings>
    <Security>
      <IdentityStore path="/etc/plcnext/Security/IdentityStores" />
      <IdentityStore editPath="/opt/plcnext/Security/IdentityStores" />
      <TrustStore    editPath="/opt/plcnext/Security/TrustStores" />
    </Security>
  </EnvironmentSettings>

  <EnvironmentVariables>
    <EnvironmentVariable name="ARP_HOME_DIR" value="/opt/plcnext" />
    <EnvironmentVariable name="ARP_SYSTEM_DIR" value="/etc/plcnext/device" />
    <EnvironmentVariable name="ARP_PATH_SYSTEM_DIR" value="$ARP_SYSTEM_DIR$" />
    <EnvironmentVariable name="ARP_PROJECTS_DIR" value="$ARP_HOME_DIR$/projects" />
    <EnvironmentVariable name="ARP_PROJECT_PLCNE_DIR" value="$ARP_PROJECTS_DIR$/PCWE" />
    <EnvironmentVariable name="ARP_PROJECT_DEFAULT_DIR" value="$ARP_PROJECTS_DIR$/Default" />
```

```
<EnvironmentVariable name="ARP_PROJECT_CURRENT_DIR" value="$ARP_PROJECTS_DIR$/current" />
<EnvironmentVariable name="ARP_PATH_USER_CONFIG_DIR" value="$ARP_HOME_DIR$/config" />
<EnvironmentVariable name="ARP_TEMP_DIR" value="/var/tmp" />
<EnvironmentVariable name="ARP_BINARY_DIR" value="/usr/lib/" />
<EnvironmentVariable name="ARP_SHADOW_DIR" value="$ARP_HOME_DIR$/shadowing" />
<EnvironmentVariable name="ARP_BACKUP_DIR" value="$ARP_HOME_DIR$/backup" />
<EnvironmentVariable name="ARP_RETAIN_DIR" value="$ARP_HOME_DIR$/retaining" />
<EnvironmentVariable name="ARP_ACF_SETTINGS_FILE" value="/etc/plcnext/Device.acf.settings" />
<EnvironmentVariable name="ARP_ACTIVE_APPS_DIR" value="$ARP_HOME_DIR$/apps" />
<EnvironmentVariable name="ARP_APPS_HOME_DIR" value="$ARP_HOME_DIR$/appshome" />
<EnvironmentVariable name="ARP_APPS_DATA_DIR" value="$ARP_APPS_HOME_DIR$/data" />
<EnvironmentVariable name="ARP_APPS_TEMP_DIR" value="/var/tmp/appsdata" />
<EnvironmentVariable name="ARP_TSM_SUPPORT" value="false" />
<EnvironmentVariable name="ARP_AXIOLINE_SUPPORT" value="$ENV_AXIOLINE_SUPPORT$" />
<EnvironmentVariable name="ARP_INTERBUS_SUPPORT" value="$ENV_INTERBUS_SUPPORT$" />
<EnvironmentVariable name="ARP_PROFINET_SUPPORT" value="true" />
<EnvironmentVariable name="ARP_PROFICLOUD_SUPPORT" value="true" />
<EnvironmentVariable name="ARP_ETHERNETIP_SUPPORT" value="true" />
<EnvironmentVariable name="ARP_OPC_UA_SUPPORT" value="true" />
<EnvironmentVariable name="ARP_EHMI_SUPPORT" value="true" />
<EnvironmentVariable name="ARP_WBM_SUPPORT" value="true" />
<EnvironmentVariable name="ARP_FWM_SUPPORT" value="true" />
<EnvironmentVariable name="ARP_PN_CONTROLLER_ADAPTER_INDEX" value="2" />
<EnvironmentVariable name="ARP_PN_DEVICE_ADAPTER_INDEX" value="1" />
<EnvironmentVariable name="ARP_INTERBUS_DRV_PATH" value="$ENV_INTERBUS_DRV_PATH$" />
<EnvironmentVariable name="ARP_USER_CERTIFICATES" value="$ARP_HOME_DIR$/Security/Certificates" />
<EnvironmentVariable name="ARP_SYSTEM_CERTIFICATES" value="/etc/plcnext/Security/Certificates" />
<EnvironmentVariable name="ARP_LICENSE_STORE_DIR" value="/etc/device_data/license_store" />
<EnvironmentVariable name="ARP_TRACECONTROLLER_SUPPORT" value="true" />
<EnvironmentVariable name="ARP_DATALOGGER_SUPPORT" value="true" />
<EnvironmentVariable name="ARP_APPMANAGER_SUPPORT" value="true" />
<EnvironmentVariable name="ARP_RETAIN_SUPPORT" value="true" />
<EnvironmentVariable name="ARP_ECLR_SUPPORT" value="true" />
```

```
    <EnvironmentVariable name="ARP_SYSTEM_WATCHDOG_SUPPORT" value="true" />
    <EnvironmentVariable name="ARP_NETLOAD_LIMITER_SUPPORT" value="true" />


    <!-- Deprecated variables just for backward compatibility-->
    <EnvironmentVariable name="ARP_ACTIVE_PROJECT_DIR" value="$ARP_PROJECT_CURRENT_DIR$" />

  </EnvironmentVariables>

</AcfSettingsDocument>
```